


Implementing your own ICC profiles into Mirage

If you are using your own ICC profiles, you can implement them into Mirage. Simply follow the easy steps below.

1) Creating The Media

Open up Mirage and go to the „*Settings...*“. Select the index “*Custom Media*“. You will see an overview of the media that is installed in Mirage. Epson and Canon media is always installed.

Click on “*Add Medium...*”



Note

„*Install Media...*“ is only used when installing Mirage Media Packages. Single ICC profiles must be implemented via “*Add Medium...*”

2) Selecting The Media Details

In the upcoming window you need to select your Printer Model, the Base Medium and a Name. If you are not sure which Base Medium is correct for you, please contact the media manufacturer. If you have downloaded an ICC profile from the internet, you might also have received a PDF file in which you can find information about the Base Medium.

After you have selected everything, click on “*Browse*” and navigate to the saved .icc file. Once the file is selected, click on “*OK*”.

Printer Model: Canon iPF8400

Base Medium: Canon Glossy Photo Paper 240gsm

Name: My Media


LUCIA EX Ink (12C) Profiles [Advanced Settings](#)

| | | |
|--------------------------------|--------------|--------|
| Fast Quality (1200x1200 dpi) | My_Media.icc | Browse |
| Normal Quality (2400x1200 dpi) | My_Media.icc | Browse |
| High Quality (2400x1200 dpi) | My_Media.icc | Browse |

OK Cancel Help

3) Finding Your Custom Media

Once you clicked „OK“, the media will appear under the selected name in your media list. You can easily find your custom medias when you click on the small left icon in the right-hand corner. This will deactivate all standard medias which are pre-installed in Mirage and leave you with your custom media. With an additional click, the standard media will reappear.



If you have any questions during the registration, please contact our support team:

Monday – Friday: 10:00am – 12:00 and 2:00pm – 4:00

phone: +49 (0) 2131 34 18 55

e-Mail: support@dinax.com